



# Label image guide

Monday, April 2, 2018 6:24 PM


1. Download labeling tool imageJ  
<https://imagej.nih.gov/ij/download.html>
2. Open ImageJ.exe




3. To open image: Drag image to the app




4. Zoom in click magnify icon, and click on(or press "+" "/" "-" key to zoom in or zoom out) the point of interest.




5. Select "freehand selection", and draw the region on image. Make it a closed loop.



6. Go to Edit-->Selection -->Create Mask. A new windows will pop up with masked image





7. Save the image in the same folder, name it with "mask\_" prefix + original image name.  
i.e. original image is 'DJI\_0040 08.jpg', masked image is 'mask\_DJI\_0040 08.jpg'